Install MiniNam on Windows 10


created by Liam Waters on 25-03-2020 (Idwat@hotmail.com) - many thanks, J


Download and install latest version of VirtualBox https://www.virtualbox.org/wiki/Downloads
Install with default settings

Download latest Ubuntu image. Example site is https://www.osboxes.org/ubuntu/


Unzip to folder on Windows PC with VirtualBox installed

Create new VM with Linux





Select attach existing hard disk and navigate to the extracted vdi



Boot image and log in

Image may update OS patches automatically. Wait till finished and reboot

sudo apt-get install python-imaging-tk

sudo apt-get install xterm

sudo apt-get install Mininet

Download MiniNam https://github.com/uccmisl/MiniNAM

Extract files to MiniNAM folder

Run sudo python MiniNAM.py from downloaded folder

Enjoy